





Machine File Creation LN-150

 Pocket 3D v15

Create Machine File



This is to create a machine file configuration in order to connect to the LN-150

- Tap Control > Machine Setup
- Tap New



Create Machine File

- Name the machine file
- Sensor type: prism
- Select the units
- Instrument: LN Series
- Vertical prism height: The height to the center of the prism from the edge of the pole
- Prism constant
 - 7.0 mm for ATP1 & ATP2 360 prism
 - 2.0 mm for A7 360 prism



Create Machine File

- Select Bluetooth > Finish

